

IT - Technical

What should my Firewall settings be?



FIREWALL SETTINGS

Server

Setup will add firewall rules, when installing on the server, to allow workstations to perform DB auto discovery and communicate with the DB. If your server uses third-party firewall software or anti-virus software that includes a software firewall such as (McAfee Total Protection, Sophos Endpoint Protection, BitDefender Total Security, Norton Security or others) then you will need to add rules in the relevant security software to allow the following:

For versions 3.2 and above:

- inward bound traffic on UDP **and** TCP port 96
- outward bound traffic on UDP 49201-49220
- inward bound traffic on TCP port 3050

Note: The above settings are the defaults and may be different if the NovaCore Data Server settings have been changed (in NovaCoreDS.ini file) or if the NovaCore workstation settings have been changed (in novacore.ini file).

For older versions of NovaCore use the following:

- inward and outward bound traffic on UDP port 49200
- inward and outward bound traffic on TCP port 96
- inward and outward bound traffic on TCP port 3050

Workstation

Windows firewall does not prevent outbound traffic and thus the following is ONLY required if you use third party security software on your workstations. Allow the following:

For versions 3.2 and above:

- outward bound traffic on UDP **and** TCP port 96
- inward bound traffic on UDP 49201-49220
- outward bound traffic on TCP port 3050

Note: The above settings are the defaults and may be different if the NovaCore Data Server settings have been changed.

For older versions of NovaCore use the following:

- outward bound traffic on UDP port 49200

IT - Technical

- inward bound traffic on UDP port 49201
- inward and outward bound traffic on TCP port 96
- inward and outward bound traffic on TCP port 3050

Unique solution ID: #1034

Author: NovaCore

Last update: 2019-08-07 05:52